

DiLand Studio

Orders Management Software

User Manual

July 2020 Version 1.2

Summary

Summary 2

Introduction	4	
Kiosk Client setur)	5
Kiosk configuration	on workflow	5
DiLand Studio set	up	6
Studio configurat	ion workflow	6
Orders Managem	ent	8
New Order		
New Creative Ord	er (Available only if Creative option is enabled)	15
PJP mode		16
Order History	17	
Configuration	18	
Initial parameter	5	
Privacy		
Digital signage		20
Photo Sources		21
Photos Visualizat	ion	22
Steps of each cor	rection command	22
Operators (valid	or operation on kiosks)	23
Import / Export d	ata	23
Import from dilar	nd 1	23
Hot folders		24
Orders to the lab		25
Orders		27
Stats		28
Remote Service .		28
Output profiles		29
Products		
Prices		
Categories		40
Index print		42
Receipt		
-	ks	47
Diagnostics	48	
-	·	
Printer status		48

Update firmware	
Export logs	
Teamviewer	
Check for updates	
Update license	
About	
Troubleshooting 50	
Local immediate print product is no longer available	

Introduction




DiLand Studio Software is a stand alone software and is also designed for central management of the kiosks. It has an operator – dedicated user interface. Installed in a "central" PC, it is possible to setup products of all kiosks (running DiLand Kiosk software) in the same local network at once and control and print all orders directly from one PC.

The software settings are done once on DiLand Studio then transferred on kiosks in a very short time. All orders received from kiosks will be saved sorted per data and per format, then the operator will decide when actually printing them.

Main features are:

- Configure products with prices at once from central pc
- Manage end user kiosks to acquire digital orders (both remote and local orders)
- import orders from other kiosks in the local network.
- print the orders anytime through the preferred output (folders, minilab, printers, etc.)
- Manage and import orders from DiLand Web

Schematic of setup example:



Kiosk Client setup

Make sure there are no previous DiLand Kiosk 2 installations on kiosks, this is to avoid software duplicates

- Install DiLand Kiosk 2, do not create products or output profiles, leave it empty
- Create only one (new) Output profile \rightarrow **DiLand**
- Set IP address or the name of the DiLand Studio 2 computer that will print \rightarrow Local server
- End user kiosks and the studio pc must be connected to the same LAN to ensure communication and proper system function.

Output profile	2					
Name		DiLand	Initial envelope numb	xer		0
Dpi X	254	Орі Ү	254	JPEG quality	(50-100)	90
Local server (computer name	or ip)					pc-studio
Auto process the orders after	import					No
channels col	or cor	rections	upload pr	ofiles	usb	devices
					OK	Cancel

Kiosk configuration workflow



DiLand Studio setup

DiLand Studio configuration

Output profiles, products and prices must always be setup In DiLand Studio.

Even in case of some products like 4x6 printed locally by the kiosks, you have to setup those local products in DiLand Studio, <u>not</u> on the kiosk settings.

Once the configuration is finished, to configure kiosks from DiLand Studio, go in Settings \rightarrow Update kiosk

Note: Update local kiosks could be automatic or manual. Check settings into "initial parameters", "auto update local kiosks after changes", Yes / No.

Studio configuration workflow



DiLand Studio 2.4.43				- 0 ×
Orders His	tory Configuration			
	System	Products	Diagnostics	\bigcirc
	initial parameters	output profiles	printer status	
	privacy	products	update firmware	
	digital signage	prices	orders in process	
	photo sources	categories	update license	
	photos visualization	index print	export logs	
	steps of each correction command	receipt	check for updates	
	operators	frames	teamviewer	
	import data	id photo to usb	about	
	export data	update local kiosks		
	imports from diland 1			
	hot folders			
				<u> </u>



System setup

Note:

1

Before you start working with DiLand Studio Software, connect and switch on the printers, after that, please run DiLand Studio. DiLand Studio Software will automatically display connected printers and loaded media.

If no printer is connected, the software will not display printer area information.

When the printer is connected to the system, within a few seconds the software will display the products window as per the connected printer(s).

Supported printers

With DiLand Studio Software you can print with almost all printers available into the market.

With DNP printers and some Mitsubishi printers it will print without installing any drivers.

Supported DNP printers are RX1, RX1HS, DS40, DS80, DS620, DS820, DS80DX and QW410.

Supported Mitsubishi printers are CP-W5000DW, CP-M1, K60, D70, D80, D90, D707.

By simple connection of the supported printer(s) to the kiosk system, the printer will automatically be recognized by DiLand Studio Software.

Color profile: The Orders Management Software uses most recent color profiles provided by the manufacturer. You can enter a color profile by entering settings / output profile.

Control panel and software management


Select the "Configuration" tab and then :

- <u>System</u>: access to the basic configuration of the software: initial animation, system backup and security, access to the management panel of digital orders, check sales information;
- <u>Products</u>: product management, output profiles, local kiosks update;
- <u>Diagnostics</u>: update software, generating log files, test receipt, check printers;



Orders Management

Orders section contains all orders received from kiosks and orders made locally. These orders must be processed manually. Here you can also suspend or delete orders



Each single print inside the order is divided by format, making possible to print full order or one print format.

Top bar:

New Order: it will start new order creation

New Creative order: it will start creation of an order with a kiosk-like workflow

Refresh: it will update orders list

Search: it will show only orders matching text entered into search field

Play/Pause: it will start or pause order processing (pausing with this command will pause all orders).

Cancel: it will exit software

Order line:

First symbol and line color will mark order as partially executed or pending. Green color like this example means prints have been printed. Order is still in the queue list because file saving on USB is still pending. Click to USB icon to start USB saving procedure

Document icon will reprint receipt ticket

Edit icon will open order to edit or redo the order Play icon will start printing of current order



Print product label will show product or products of an order. There will be a lable for each product of an order. By selecting the small pause button into each product label it will pause printing only of that print format.

Pause icon will pause printing of full order.

Trash bin icon will delete current order

Shortcut: by keep pressed the CTRL key on keyboard it is possible to select printer for each order line. Only printers suitable for print product are displayed.

Bottom:

🕦 DiLand Studio 2.4.43.43				- 0 ×
Orders History Configuration				
new order new creative order	ی ک			
A 5620 FW 1.52		31	B FW 1.05	5
DS6X53002140 15x20			D28X68000042 20x30 (PP)	
DS620-RO.icc Change ICC			PP_DS820_0010.icc change ICC	

It shows an area for each connected printer

When printing it will change color and show printing progress.

In case of printer error it will be red color and short explanation of the error.



New Order

DiLand Studio 2.4.43.43	- ō ×
Orders History Configuration	
new order new creative order C	
63 29/06/2020 17:24:03 0,00 € Laura B	10x15 (4) 20x30 (1)

In addition to orders received from connected kiosks, it is possible to create print orders also within DiLand Studio software.

To create a new order click either on new order or new creative order button. This will create a new order tab. It is possible to open multiple orders at same time.

New order will start new order with DiLand Studio workflow. Only standard print products like prints and prints with frame will be available.

New creative order will start new order with a DiLand Kiosk kiosk-like workflow. All products will be available, calendars and photobooks included.

This is workflow for new order button:

DiLand Studio 2.4.43.43		- @ ×
Orders History Configuration		
new order new creative order 🛛 🖍	Select the photo source	
63 29/06/2020 17:24:03 0,00 € Laura B	From a system source: From a directory: Memory card USB device CD/DVD Local network iPhone and iPad Android Bluetooth Desktop C.\ Import Close	10x15 (4) 20x30 (1)

1) Select new order button, it will open image source selection window

2) Images can be loaded from various digital sources: Memory Card, USB devices, CD/DVD, Smartphones, Tablets and Folder.

3) Select on the screen from which digital media type you want to load images or select a folder.

The visualization criteria depend upon on the media type.

4) After folder selection a new screen will open



This an operator-intended screen best operated with keyboard and mouse.

Click on image to select it. Multiple image selection is possible with same rules of file selection of Windows File Explorer: click on one image and then by shif-click on second image it will select all images from first image to second selected image. CTRL click on an image it wil add or remove it form selection.

Description of buttons on right panel – Main Tab

<u>All/none:</u> will select all or deselect all images.

Zoom: will enlarge or reduce size of thumbnail images on the screen

<u>Copies:</u> will increase / decrease copies of selected images (will work only if images are associated with a product)

<u>Duplicate</u>: will duplicate selected images (as an example, this is useful to print multiple products with same image)

Add photos: will open image selection window to load more images

Select product: will open a window to select product to be associated to selected images

Rotate: will rotate images 90 deg clockwise or anti-clockwise

<u>Fit/Fill</u>: will select if printing full image (Fit) eventually by adding two white borders or crop image (Fill) according to print product aspect ratio (print area will show as yellow area in the thumbnail).

<u>Print 1/1:</u> this procedure allows to print a part of an image with precise dimension in the final print. This could be useful in case of forensic prints or for products like a 1 to 1 poster of a child. Draw a line by click and drag then select length in millimeters and print product. The length of the drew line will be printed with the set size in millimeters. Note: red line will not actually print.



Description of buttons on right panel – Product Tab



Buttons with same name are same as Main tab

<u>Print products</u>: This section has a button for each product set on the unit. By selecting a product this will be associated with all selected images.

<u>Hide non available products</u>: by checking this box only available products will be listed (based on connected and available printers). By unchecking this box all products will be listed. <u>Glossy / Matte</u>: will select glossy or matte finish to selected images

Description of buttons on right panel – Correct Tab



Eventually scroll items with mouse wheel or with right bar to show all items

<u>Original:</u> will reset image to original (no corrections)

Enhance: will apply automatic local density correction

Intensity: will set intensity (strength) of automatic enhancement

White: will set white boost of automatic enhancement

Black: will set black boost of automatic enhancement

<u>Red eye:</u> will apply automatic red eye correction. By pressing again "+" button it will increase strength of red eye correction. Maximum strength is 3.

Red / Green / Blue: it will increase or decrese level of the 3 primary colors

<u>Brightness / Contrast / Saturation / Sharpness:</u> will increase or decrease the selected parameter. Values are from -100 to +100.

<u>Levels / Contrast / Color:</u> will apply an automatic correction based on automatic distribution of intensity of each color

<u>Effect:</u> following effects are available: Black / White, Sepia, Negative, mirror on vertical axis, mirror on horizontal axis.

<u>Save as new preset</u>: current mix of corrections can be saved with a name and then be applied later to selected images. A button will be created with the name of save correction. To remove or edit a saved correction, right click on its button.

<u>Copy / Paste:</u> will copy and paste all corrections from selected image to newly selected image <u>Apply until end:</u> will apply current corrections to all images following selected image <u>Apply on all photos:</u> will apply current corrections to all images

Description of buttons on right panel – shortcuts

Orders History Configuration New order $(\mathbf{\hat{n}})$ Main Product Corre original × × ~ enhance + + + red eye Q product A correct ? R reset crop сгор T tilting E red eyes Split between printers Priority order 10x13 x

Shortcuts are made by keep pressing a letter on the keyboard and at same tiem operating with the mouse

<u>?:</u> it will show list of all shortcuts

<u>Q product:</u> it will show on right panel the list of products

<u>C crop</u>: by operating with mouse wheel it will zoom on the image and by click and drag on the yellow box it will move cropping area


<u>R reset crop:</u> it will reset crop to full image

T tilting: it will show a reference grid and by operating mouse wheel it will rotate image

A correct: it will show correction commands on right panel

<u>E red eyes:</u> it will apply red eyes correction (intensity set to 1)





<u>Index print</u>: it will add index print to the order. Index print settings are made in the configuration area under "products" column

<u>Priority order</u>: it will set high priority to the order, it means this order will jump as first on the list of pending orders. As an example this could be useful in case of passport print.

<u>Trash bin</u>: it will delete current order <u>Disk</u>: it will save order in the order list <u>Play</u>: it will save the order and submit it to printing cue

New Creative Order (Available only if Creative option is enabled)

New Creative order will start a kiosk-like workflow. Please refer to DiLand Kiosk manual for details on this workflow.





PJP mode

PJP mode (Preview, Judge, Print) is a printing mode similar to that of some minilabs. The initial workflow is same as kiosk workflow.

After selecting images a PJP screen is shown.



This screen is designed to be operated by mouse and keyboard.

It starts with first image selected. By pressing space bar it will select next image. It is possible to select any image with a mouse click.

On selected image:

- By selecting the product it will open product selection page and it is possible to change product.
- Button on the bottom of the page will change Brightness, Contrast, RGB, Gamma, Saturation and Sharpness.
- Other buttons are for reset to original image, copy corrections to all following images, automatic correction, Red eyes correction, Number of copies, Black and White, Sepia, Rotate 90 degrees, Fit /Fill, Delete order, save order.
- Bottom right there is play button to finish corrections and print the order.
- **Keyboard Shortcuts:** holding "C" key and operating with mouse wheel will change crop area, click and drag will move crop area.

F and V keys will increase and decrease Brightness, G / B for Red corrections, H / N for Green, J / M for Blue.

Order History

Select the History tab

Diland Stu 10 2.4.43 Orders His	story Cinfiguration				- Ø ×
recreate orde	er use photos 🖪 🛍	م 🗉			
Number	Date	End user name	Price	Products	
47	22/06/2020 15:11:05		0,00€	20x30	<u> </u>
48	22/06/2020 15:13:26		0,00€	20x30	
49	22/06/2020 15:33:33	chiara	0,00€	20x30	
50	22/06/2020 16:50:39	m	0,00 €	20x30	
51	22/06/2020 16:54:59	m	0,00 €	20x30	
52	22/06/2020 17:20:40	m	0,00€	20x30	
53	23/06/2020 11:07:51		0,00€	20x30	
54	23/06/2020 11:30:09		0,00€	20x30	
55	23/06/2020 11:54:45		0,00€	20x30	
56	23/06/2020 11:56:07	g	0,00€	20x30	
57	23/06/2020 17:11:57	9	0,00€	20x30	
58	23/06/2020 17:13:41		0,00€	20x30	
59	25/06/2020 11:36:13	grid	0,00€	20x30	
60	25/06/2020 11:39:17	test	0,00 €	20x30	
61	25/06/2020 11-53-21	+	000 €	20v30	

Select on order line and then:

Recreate order: it will create a new order with images and products of selected order.

Use photos: it will create a new order with images of selected order. There will be no product information associated with images.

Save: it will export order images into a specified folder.

ID photo to USB: in case of passport print order it will save ID photo to USB

Delete: it will delete selected order.

Document: it will print the receipt ticket.

Search: it will perform a free text search within the order numbers and end user name information.

Configuration

Select configuration tab

DiLand Studio 2.4.43.43				– 19 ×
Orders History Configu	ration			
Sys	item	Products	Diagnostics	
init	ial parameters	output profiles	printer status	
pri	vacy	products	update firmware	
dig	ital signage	prices	orders in process	
pho	oto sources	categories	update license	
pho	otos visualization	index print	export logs	
ste	ps of each correction command	receipt	check for updates	
оре	erators	frames	teamviewer	
im	port data	id photo to usb	about	
ext	port data	update local kiosks		
im	ports from diland 1			
hot	t folders			\bigcirc

Initial parameters

Choose "System" > "Initial parameters".

	Initial parameters p	¢.	Initial pa	ramete	rs		
9	Language Inglese / English (EN)	5	External working d	lirectory			
	PIP mode No S		Centralized configu	ration code			
	Last order envelope number 64		Kiosk code for the l	InTouch 24/7 serv	ice		
ii r	Number of days before order elimination 10	f r	Program tags				
	Image quality verification Medium	i	VAT Rate	0,00 %	Display as	Vat	
	End user name is required Yes		Auto "update local	kiosks" after chang	ges	No	
la	External working directory	ē	Supports multi-lan	guage config.		No	<
	OK Cancel			- M M M	ОК	Cano	el



- Language: select language for the DiLand Studio software
- **PJP mode:** set PJP mode "Yes" or "No". Default is "No". Please refer to PJP mode paragraph.
- Last order envelope number: set starting number of order numbering sequence. If not set it will start with 1.
- **Number of days before order elimination**: specifies the number of days after which orders already processed are deleted from the system memory.
- Image quality verification: it sets level of image resolution below which a warning for low quality is displayed. If set to "High" the warning will appear if image resolution is less than 300 DPI, if set to "Low" warning is displayed when resolution is less than 150 DPI.
- End user name is required: if set to "yes", user name input page will be displayed at the end of the workflow.
- **External working directory**: select a directory to save processed orders. Could be on a separate disk. As an example this could be useful in case of system on a SSD to save orders on a separate HDD.
- Centralized configuration code: this is used in case of control of multiple shops from a central location.
- Kiosk code for InTouch 24/7 service: this is used for central reporting in case of multiple shops
- Program tags: tags to enable special functions for some customers
- VAT rate: enter appropriate VAT rate for the country. If set to 0 (zero) no VAT will be added.
- **Display as**: set VAT or TAX. This will affect text printed on the receipt ticket.
- Auto update local kiosks after changes: if set to yes it will automatically update local kiosk after changing settings. If set to no (default) kiosks will be updated only when selecting "update local kiosks" in products settings column

Privacy

It is possible to setup and display a text with privacy policy of the shop.

	Privacu	e
	Privacy Display privacy policy	s
	No	e
je	Information Controller	t
P	Keep user images encrypted	f
	Yes	vi
	load your privacy policy reset	
	OK Cancel	
	14	



Digital signage

It is possible to set animations and display advertisements on connected kiosk screens when the kiosks are idle.

It is possible to display images, videos, html pages, fade-in effects and customized text.

Pictures and videos are displayed in same image ratio as the monitor. It's preferred to use images and / or video with same resolution of the monitor. Small images may be not sharp enough, too large images may have slow transitions and slow down the PC.

If no setup then the default video is displayed.

To setup a new image or video sequence select new and then:

DiLand Studio 2.4.43.43		5 X
Orders History Configuration		
	Digital signage	
	🕂 new 🖉 edit 🗊 delete 🕐 up 🕢 down 🐵 export	
	Resource Animation Image Random image Sequence Video Web page Web page in single file (.mht)	
	OK Cancel	
	€ back	

- Animation: it is a slide show of minimum 6 images.
 Select: New Animation OK
 Drag and drop inside the animation at least 6 resources (e.g. images). Move the resources by using upper arrow buttons.
- Image: Image shown for a minimum duration in seconds.
 Choose .jpg or .png images. It's preferred to use images and / or video with same resolution of the monitor. Files too small may not be clear, files too large slow down the software.
 Select: New Image File name: type the path an confirm with OK
- **Random image:** The images stored in the selected directory will be displayed in random sequence. Select: New Random image directory then select the directory containing images.
- Sequence: Video or images displayed in sequence.
 Select: New Sequence OK
 Drag and drop inside the animation at least 6 resources. Move the resources by using upper arrow buttons.
- Video: Choose .avi , .mp4 video, animated gif
 Select: New Video file name: type the path of the video OK

Photo Sources

	Producto	Disaportice
Photo sources		
Favorite directory 1		C:\Sample Images
Favorite directory 2		
Favorite directory 3		
Display file names Yes	Show image resolution	Show image proportion
Show raw files No	Image quality verification Medium	Minimum file size of the images (in KB
Display all photos horizontally		Nc
	[OK Cancel

Use this section to enable various sources from which customer can upload images to Diland Studio Software.

- **Favourite directory 1-3**: it is possible to setup up to 3 directories from which users can load images clicking on a button on image loading screen.
- Display file names: if set to yes it will show a label with file name below loaded image
- Show image resolution: if set to yes it will show the image size in pixels
- Show image proportion: is set to yes it will show image ratio (2:3, 3:4 etc.)
- Show RAW files: if set to yes it will show and load RAW files.
- Image quality verification: it specifies level of image resolution below which a warning for low quality is displayed. If set to "High" the warning will appear if image resolution is less than 300 DPI, if set to "Low" warning is displayed when resolution is less than 150 DPI.
- **Minimum file size**: if set a value in kB, all smaller images are not displayed. This is useful to avoid loading small images like thumbnails.
- **Display all photos horizontally**: if set to "Yes" all images will be displayed horizontally even if they are portrait images. This could be useful in case of PJP mode as in this case all images will have same area size on the screen.

Photos Visualization

Use this section to manually setup the grid for photos visualization on the screen. It is possible to setup number of rows and columns.

It is also possible to set if images with embedded color profile should be used by appling the color profile (YES, default) or NO.

Please note that not using embedded color profile could result on bad colors on screen and on print for that image.

Photos visualizatio	n
Default sorting	Default
Columns in photo selection (O = auto) O	Rows in photo selection (O = auto) O
Columns in order editing (0 = auto) ()	Rows in order editing (0 = auto) O
Use embedded color profile	Yes
	OK Cancel

Steps of each correction command

It is possible to setup the magnitude of change for each step of color corrections and other parameters of images. The higher the value the coarser the change.

By changing default value it will apply to all parameters.

Steps of each correction command							
Default 3	^{red} O	green	0	blue	0	gamma (C
brightness	contrast O	0	saturat	ion (0 sha	arpen (C
			(Ж		Cancel	



Operators (valid for operation on kiosks)

It is possible to setup multiple Kiosk operators so each order may be linked to one operator.



Import / Export data

Export data will save into a zip file DiLand Studio settings. Useful for backup copy of settings and to transfer settings from one unit to another.

Import data will load a previously saved setup zip file.

Import from diland 1

Import settings from previous version 1 software.



Hot folders

Hot Folder Print is available from Windows folder.


Hot Folder Print function allows instant print of images as they are dropped (copied) into a folder. There is one folder for each available print size. Folder name is same as related print size.

As an example, to print a 10x15 cm sheet copy an image into folder: "C:\Hotfolder\10x15".

The following image types are accepted in this version of Hot Folder Print:

- JPG/JPEG
- TIF/TIFF
- PNG
- BMP

To setup Hot Folder Print, enter Configuartion tab and then select "hot folders" and then select "new" or "edit"



The Hot folder settings window will show:



Hot folder p	Hot folder
Directory C:\Hotfolder	Default quantity
Enabled Yes	Paper type Glossy
Default quantity 1	Use default borders
Paper type Glossy	Partial matte Disabled
Use default borders NO	Keep the photos in an archive for these days ($0 = no$ archive)
Partial matte Disabled	Auto process NO
Keep the photos in an archive for these days (0 = no archive) 0	Wait for end of multiple files copy
OK Cancel	OK Cancel

Description of each parameter:

Directory: it is possible to set parent directory for hotfolders

<u>Enabled</u>: set Yes or No. If set to "No" the hot folder print function will be disabled. All settings will be kept in place.

<u>Default quantity</u>: set default number of prints for each image copied into each folder.

Paper type: set the paper finish to be used by all print sizes

<u>Use default borders</u>: set Yes or No. If set to yes, images will be printed combined with PNG graphics set into the product settings.

<u>Partial matte</u> (only for DNP printers): select form Diasabled / Matte / Fine Matte / Luster. If set one of the 3 possible finishes, it will perform partial matte finish using the graphic set into the print channel.

<u>Keep the photos in an archive for these days</u>: set number of days printed images will be saved into "C:*parent directory*\Archive" folder. If set to 0 (zero) images will not be copied into Archive and will be erased from the hot folder immediately after printing.

Autoprocess: if set to yes images will be printed immediately after copy into the correspondent folder.

<u>Wait for end of multiple files copy</u>: if set to yes software will wait few seconds before printing thus allowing additional images to be copied into hotfolder.

Orders to the lab

In case of order transfer to a remote server, it is possible to set following two parameters

DiLand Studio 2.4.43.43							- 0 ×
Orders History	Configuration						
	prioco 3001 cc3		Categories	apaar		1	
	photos visualizatio	n	index print	expor	t logs		
	steps of each corr	rection command	receipt	check	for updates		
	operators		frames	team	viewer		
	import data	Orders to the	e lah				
	export data	Number of minutes before o					
	imports from dila			15			
	hot folders	Create transfer orders in the	lab as 'Suspended'	No			
	centralized config		ОК	Cancel			
	passwords						
	orders to the lab						
	orders						
	stats						

Number of minutes before orders auto upload: it is possible to set delay time in minutes. Set to 0 (zero) will upload order immediately. Default time is 15 minutes in order to prevent wrong orders to be transferred to the lab.

Create transfer orders in the lab as "Suspended": if allowed by the lab workflow software the order is transferred and put to an "on-hold" condition.

Orders

🕦 DiLand Studio 2.4.43.43	- 0 ×
Orders History Configuration	
Orders	
🕟 process 河 export photos 河 export order 💿 reprint receipt 🗊 delete	13
▲ 22/06/2020	٢
⊿ 47 - b	
20x30 Glossy x 1 - Dnp - 20x30 (envelope n. 47)	
⊳ 48 - n	
⊳ 49 - chiara	
⊳ 50 - m	۲
	print page
	print until end
00-PrinterTestpg	
\bigcirc back \bigcirc next	

In this section there is list of processed orders (orders history).

By selecting an order it will be possible to:

Process: it will process again the selected order. A copy of the order will be created.

Export photos: it will export all images used into selected order to a specified folder.

Export order: it will export order images into a specified folder.

Delete: it will delete selected order.

Print page: it will print only selected page.

Print until end: print all pages from selected page to last page.

Stats

DiLand Studio 2.4.43.43							- 0 ×
Orders History	Configuration						
			Sta	ats			
		💼 reset (export to	excel 💿 export a	s xml		
Group by:		Group by:		Group by:		Group by:	
None	$(\mathbf{\hat{T}})$	None		None	$(\mathbf{\hat{T}})$	None	
Product		Product		Product		Product	Ŭ
Paper type		Paper type		Paper type		Paper type	
Output profile		Output profile		Output profile		Output profile	
Channel		Channel		Channel		Channel	
Media input		Media input		Media input	٩	Media input	
No. of orders Total pri	ints Avg. prints	Total price Avg. price					
41 113	2,76	0,00 € 0,00 €					
			€t				
			Ð	Dack			

In the statistics section it is possible to view production statistics of the system.

It is possible to filter the information visible on the screen.

It is possible to export the data in an Excel or to an xml file for further analysis.

Remote Service

These parameters will be used for web platform statistics.


Insert Machine Group, Machine code and Machine description as received from your dealer.

👰 DiLand Studio	2.4.43.43				
Orders	History	Configuration			
		operators		frames	team
		import data		id photo to usb	about
		export data		update local kiosks	
		imports from dila	Remote ser	vice	
		hot folders	Machine group		
		centralized config	Machine code		
		passwords	Machine code		
		orders to the lab	Machine description		
		orders			Canaal
		stats		ОК	Cancel
		remote service			
		city lab (diland we	eb)		

Output profiles

In this section it is possible to create and edit output settings.

Example of DNP output settings



- Name: it is possible to change output profile name
- Resolution: Option to choose 300x300 dpi or High Quality printing 300x600 dpi.
- Initial envelope number: set the starting number for order number. In case of multiple terminals could be convenient setting different starting numbers in order to indentify used terminal out of order number.
- JPEG quality: set a number from 50 to 100 for JPEG quality. 100 means highest quality and larger file, 50 means lower quality and smaller file
- **EAN code:** in addition to product specific EAN code, it is possible to print a receipt ticket with an output specific EAN code.

- Message on order processed (on screen): it is possible to set a text message to be displayed on screen at end of the order printing
- Message on order processed (on receipt): it is possible to set a text message to be printed on the receipt at end of the order creation (before end of printing).
- **Print order separator:** if set to yes it will print a white print with order information at end of the order.
- **Minimum prints (order separator):** order separator will be printed only if total number of prints is above the number set for this parameter
- Verify the remaining prints before accepting the orders: if set to yes, order will be accepted only if available prints are higher than number set in Safety stock parameter.
- **Can split orders on many printers**: if set to "yes" one order will be sent to all printers able to process that order (an order of 20 prints 4x6 with two DS620 connected and 6x8 media loaded will be split 10 images per printer).
- **Custom color profile**: it is possible to load a color profile to be used by each printer model. If no profile is set then default profile is used.
- **High density print on supported printers**: if set to yes it will enable high density mode on printers with such a capability like DS820.
- Print panorama print only on these printers: it is possible to select the printer or printers for panorama printing. This may be convenient in case only one or few printers have enough space in front area to accept panorama print sizes.
- Auto process the orders after import: is set to yes, orders received from kiosks will print immediately without confirmation. If set to no, orders will be on hold waiting for operator confirmation.
- **Process directly on the kiosk**: if set to yes, orders will be printed locally at kiosk if suitable DNP printer is connected to the kiosk.

<u>Channels</u>: it will open a new window. It is possible to select an output channel and edit it.



- Name: it is possible to edit the output channel name
- **Resolution**: it is possible to override the output profile resolution setting and set a print resolution, like 300x300 or 300x600, only for selected output channel.
- JPEG quality: it is possible to override the output profile JPEG quality settings and set a JPEG quality only for selected output channel.
- **Printer to use**: it is possible to set a printer for selected output channel.
- **Partial matte (horizontal and vertical)**: it is possible to set a partial matte graphic for selected output channel. Partial matte graphics must be selected in pairs: one for horizontal (landscape) images and one for vertical (portrait) images.

A partial matte image is a JPEG file with white background and black graphics. Must have same aspect ratio of selected print channel. In correspondence to black graphic the printer will apply the paper finish selected into Hotfolders / Partial matte settings.



Color corrections: it will open a new window

DiLand Studio 2.4.43.43							3	- 0 ×
Orders History	Configuration							
	System (Dutp	out profile					
	initial p	-ligh D	color correctio	ons		Ì	-	
	digital		Color profile				e iS	
	photo s		Auto color NO	Auto contrast No	Auto levels No			
	photos steps c	Back p	Brightness (from -100 to 100) O	Contrast (from -100 to 100) O	Saturation (from -100 to 100		25	
	operati		Red (from -100 to 100) 0	Green (from -100 to 100) 0	Blue (from -100 to 100) (
	import		Gamma (from -100 to 100)	Sharpen (from		€		
	export			0	(
	import			C	K Cancel			
	hot fold				OK Ca	ncel		

- **Color profile:** it is possible to load a color profile to be used for all DNP printers output. It is not reccomended to load color profile in this position. It is better to load a color profile for each printer.
- Auto color: all images will be enhanced with Auto color function before printing
- Auto contrast: all images will be filtered with auto contrast function before printing.
- Auto levels: all images will be filtered with auto levels function before printing.

- Brighness, Contrast, Saturation, Red, Green and Blue: set a value from -100 to +100 to adjust all images before printing
- **Gamma:** set a value from -100 to +100 and all images will be enhanced with Gamma function before printing.
- Sharpen: set a value from 0 to +100 to sharpen images, from 0 to -100 to blur all images before printing

Color corrections per printer: it will open a new window, select a printer and select "edit":

	D	Color cor	rrectio	ons for	specifi	c printe	rs		
	Pr	Model		DS620	Serial number	DS6X530	002140		D
		Paper type High Glossy	Density print	t on supported pr	inters		False		
Color corrections per printer	51	Apply this color con	rection				No		
g edit	a	Color profile							
DS620 (DS6X53002140) Fine Matte	a,	Auto color	No	Auto contrast	No	Auto levels	No		
e DS620 (DS6X53002140) Luster		Brightness (from -1	100 to 100)	Contrast (from -	-100 to 100)	Saturation (from	-100 to 100)		D
DS620 (DS6X53002140) Glossy [[DS620 (DS6X53002140) Matte		Red (from -100 to 1	100) O	Green (from -10	0 to 100) 0	Blue (from -100 t	o 100) O	●	
Close						ОК	Cance	2	

• It will open a new window and it will be possible to apply settings, color corrections and enhancements only for selected printer and for selected paper finish.

Products


Choose "Products":

DiLand Studio :	2.4.43.43				- 0 ×
Orders	History	Configuration			
		System	Products	Diagnostics	\bigcirc
		initial parameters	output profiles	printer status	
		privacy	products	update firmware	
		digital signage	prices	orders in process	
		photo sources	categories	update license	
		photos visualization	index print	export logs	
		steps of each correction command	receipt	check for updates	
		operators	frames	teamviewer	
		import data	id photo to usb	about	
		export data	update local kiosks		
		imports from diland 1			
		hot folders			•
					<u> </u>

Select a product and click "edit"



Print & Print with frame



It allows selecting:

- Channel: select output channel for the product
- **Paper type:** select paper finish. By default the finish choice is manual so software will prompt page with finish selection during order creation.
- Visible: user can make each print size visible or not, under this product category. The print formats/sizes will be visible also based on information of printer model and media loaded.
- Apply crop by default: Select yes or no. If set to yes all images will be cropped to fill print sheet.
- Minimum number of photos: set minimum number of images for current product.
- Max. number of photos: set maximum number of images for current product.
- Auto index print: if set to yes it will add index print to print order
- Auto archive on USB: if set to yes, at end of print workflow software will prompt to save all images of the order to a USB memory.
- Default horizontal frame / Default vertical frame: it is possible to select a frame from existing library or from any image source. Frames must be inserted in pairs: one for horizontal (landscape) printed images and one for vertical (portrait) printed images. A frame is a PNG file with transparency in the area where user image will be displayed.
 Frame must have same aspect ratio of the print channel.



- Add to add format: if set to yes, current print format will be listed into "add format" list.
- **Top, Bottom, Left and Right margins:** set white margin in millimeters on correspondent side of the print. Please note that due to paper trimming the white margin on print sheet will be less than set value. Please adjust according to paper trim size of connected printer.
- **Print in partial matte:** if set to yes, partial matte printing will be enabled on current print size.
- Partial matte (horizontal / vertical): Partial matte graphics must be selected in pairs: one for horizontal (landscape) images and one for vertical (portrait) images.
 A partial matte image is a JPEG file with white background and black graphics. Must have same aspect ratio of selected print channel. In correspondence to black graphic the printer will apply the paper finish selected into Event mode settings.
- **Default category:** it is possible to select category for current print product. If set to "Auto" the category will be automatically selected by the software.
- **Price visualization mode:** it is possible to select from various price visualization modes. Default is "visualize all prices"
- **Product code:** set product code. Valid in case of product code management, as in case of photo lab output (optional feature).
- **Priority:** select priority for current product among High, Normal and Manual confirmation. In case of priority set to High, the orders in process will be paused and current product printing will start. This could be convenient in case of urgent products printing like passport prints.
- Weight (in grams): set weight for single product weight. This will be used in case of shipment cost calculation. Available only in case of lab printing option.
- VAT rate: if set VAT rate in percentage, the receipt ticket will show also VAT amount.
- **Barcode type:** select suitable barcode type among list of available barcodes. Barcode will print to receipt ticket.
- **EAN code:** set product code number to be printed according to barcode type set above.
- **<u>Box</u>**: it will open a new window to set product selection button appearance.



Box Description	
Visible Begin date End date Visibility on klosks Yes 01/01/1900 31/12/2999 Visibility Badkground color Custom background color Text color Default Font Font	
kon Background image Password <not changed=""> Variable Supported languages OK Cancel</not>	Prints

- Description: insert text for product name (Prints in this example)
- Visible: if set to "No" the product will not show on product selection screen
- Begin / End date: set starting date and finish date for product availability
- Visibility on kiosks: this setting is valid only for visualization on connected kiosks
- Background: it is possible to set a background color from a palette or a custom color.
- **Background image:** instead of a uniform color it is possible to set an image as background image. Suitable image is a JPEG file. Reccomended resolution is 500 x 500 pixels.
- Font: select font to be used for text
- **Icon:** set an image to present the product. Suitable image is a PNG file with 500 x 500 pixel resolution.

Product	Price
10x15 Grennel Paper type Visible it Prices	From quantity Price Calculation mode s 1 € 0,35 Replace
For end user photos For event photos	Fix fee € 0,00
⊕ new ⊘ edit (m) delete Close	Service fee € 0,00
3 Rold to Rold Format box prices aliases frames	OK Cancel

• **<u>Prices:</u>** it will open a new window. Select new to insert a price.

- From quantity: set starting quantity for related price. Normally it is "1" unless setting price brackets.
- **Price:** set price in local currency
- **Calculation mode:** valid only in case of price brackets. Select "replace" or "add". In case of "replace" all items will have same price, related to total quantity. In case of "add" the lower price will be valid only for quantity above the price bracket.

Example: print price 0,35 Euro from 1 to 19 and 0,29 Euro above 20 prints, customer prints 25 copies.

In case of "replace" the total amount will be 0,29 x 25 = 7,25 Euro

In case of "add" the total amount will be 0,35x19 plus 0,29 x 6 = 8,39 Euro

- **Fix fee:** set a fix amount to be added for each type of ordered product. In case of order with multiple products all Fix fee amount will be added to total amount.
- Service fee: set a fix amount to be added to total amount for the product. In case of order with multiple products only one service fee will be added to total amount. If service fee is not the same for all products, it will be added the highest value.
- Aliases: it will open a new window

Paper ty 10x15 on Dnp	_{jpe} Visible Yes
n number (+ new) (edit () delete	Yes
tex print Close	0 No
horizontal frame Derauit vertical frame Add Format box prices aliases frames	

Select "new" and insert one or more alias for current product.

Product alias is a convenient alternative to the setup of two identical products with name as only difference.

As an example, could be convenient setup of "001" as alias for the 10x15 print product to be linked to a "001" hotfolder or to a "001" print channel from another terminal with DPOF output.

• **Frames:** it will open a new window.

Photo Packages 10x (10x - Fo		10x15 on Dnp	Yes		
Frames		Choose the object to create			
河 new category 🕀 new	🔊 edit	Coloured border	own	(cut	🐵 paste 🐵 imports
	<u>۲</u>	Frame from .png file			
		OK Cancel			Close
	Default horizo	ntal frame Default vertical frame			

It is possible to insert frames which will be available only for current product. In case of insertion of one frame or of a pair, horizontal and vertical, the frame will be automatically added to the customer image without selection on order workflow. If more frames are added, a frame selection screen will show during print workflow. For more information on frames please go to the "Frames" paragraph.

Passport Photo

The operator can configure the passport default parameters by selecting passport photos and click on the edit control.

Product						
Name						
Channel	s	undefine		per type	visible Yes	
orientation Horizontal	Rows	2	Columns		5	
Høght (in mm)	45 <u>,</u> 00	Width (in mm)	3!	5,00	Ì
Reply crop by default Yes	Horizontal spa	cing (in mm) 0,00	Vertical sp		"") 0.00	j
Include portrait	Print cut heipe	rs	Logo			
box prices	aliase	s load t	from t	temp	late	
passport p	paramet	ers				
			ОК		Cano	el

The operator can change all the parameter values in the product info and also for the passport parameters:

Passport parameters		
Face representation Oval		Ability to change from Oval to Rectangle
Min face height (in mm) 31,00	_	Min face Height in mm
Max face height (in mm, 0 – auto) 36,00		Max face Height in mm
Min face width (in mm, 0 = auto) 16,00	_	Min face width in mm
Max face width (in mm, 0 = auto) 21,00		Max face width in mm
Min distance from the eyes (horizontal line) to the bottorn (in mm, 0 – auto) $0,00$		Min distance from eyes
Max distance from the eyes to the bottom (in mm, 0 – auto) $0,00$		Max distance from eyes
OK Cancel		



- 1. Only one template can be saved i.e. settings for only one template
- 2. All the parameter values must be entered in mm
- 3. Multiple templates are not supported

AL Y


Prices

To setup prices an external keyboard is needed.

DiLand Studio 2.4.43.46

Orders History	Configuration			
	Sustem	Products	Diagnostics	
Prices				
	@ e	kport prices 💿 import pric	es	
Passport photo				\odot
Photo Package				
Print	Visible copy prices	paste prices		
	Per product quantity			
	From Price Fix fee Service f 1 € 0,35 € 0,00 € 0,00	20		
For end user p				
For event phot	0S 1∩√I			
				Close
	not tolders			

- Visible: White check (ON) means the product is visible to the customer.
- Add remove: add or remove a price value. To enable product pricing it is necessary to add at least one price.
- From: minimum numbers of copies for current price break.
- **Price**: price for one unit of product (example: price for one print).
- **Service fee**: fixed price for order. In case an order with multiple service fees only the maximum service fee will be added to the total.
- Copy prices / paste prices: function to copy and paste the prices from one product to another.



Categories

Categories management section allows to group products, even in multiple levels, to simplify or encourage customer's product selection.

DiLand Studio	2.4.43.46						17	- 0 X
Orders	History	Configuration						
		System initial para	nmeters	Products output profiles	Diagnosti printer st	8 88		Ť
	Categ	ories						
	问 nev	v category 🧭) edit í 🗊 delete 🕟 ne	ew page 🕥 up 🕔 dov	wn 🕲 cut (🕐 p	aste 💿 regenerate	
	l Prin ⊳ Fo					49 	⊳ Folder ⊳ Dnp	
	⊳ Ex	press prints				€	 Epson SL-D700 	
		o Packages port photos						
	Ita	ly - Passaporto	o (35 mm x 40 mm) (Dr	(qr				
							Close	
		hot folder	S					(\mathbf{A})

Several actions are allowed through commands listed on the top of this page:

- Regenerate: automatically regenerate the categories based on product settings (Products menu).
- New category: it allows to create a new category.
- Edit: it allows to edit setup of the selected category.
- Delete: to delete the selected category.
- New page: this feature allows you to insert a page break in order to organize the category buttons on the customer's screen.
- Up: Down: this feature allows you to change the position of the selected category in order to change the visualization sequence of the categories on customer's screen.

The remaining part of Categories screen is divided into two parts. In the left side there are the tree structures as they show on the customer's screen. In the right side there is list of all products sorted by output profile.

To group products into an existing category, drag and drop the selected product from the list on the right to the relevant category on the left. It is possible to enter a product in more than one category.

To create subcategories: Select the main category, then proceed with creating a new category or by drag and drop a category into another.

When you create a new category the following fields must be completed:

	Category	59
£	Name	
20	Customized title	(¢)
	Description	
	Visible Begin date End date Visibility on kooks Yes 01/01/1900 31/12/2999 Visibility	6
	Background color Custom background color Text color Default	
3	Font	
	kon Background image	•
		cel

- Name: this is the name of the category as it will be on the customer's screen.
- Customized title: inserted text will be visible on top of user screen after category selection
- Description: additional information on the category button on customer's screen.
- Visible: it specifies if the category will be available on the customer's screen.
- Begin End date: you can choose a date by which the category is available.
- Icon: you can choose an image that is displayed as an icon within the category button box. We recommend choosing a small image.
- Background image: you can choose an image that is displayed as a background inside the category button box.

To order the sequence of categories and products as they will be on customer's screen: select the category or product and move it up or down with the arrow keys on the menu.

On customer's screen the categories and products sequence will be shown as by the directories tree structure setup. To display a category on top of a new page, select the category and click the New Page command in the menu.



Index print

Within print products it is possible to add an index print with print order. Index print is also available as product. Settings of index print within "product" settings are separate from settings of this section.

Index print	D
Enable index print Yes	
Mode On the same format of prints	
Fix fee € 0,00	
Rows Columns 6	
Header Index Print	
Logo	
Label on images File name	
OK Cano	cel

- **Enable index print:** set yes or no. If set to yes, an index print will be added to print products. There is no need to enable index print on print product settings.
- Mode: it is possible to print on same output of the print order or to a specific print format.
- **Fix fee:** set a fix fee amount. This amount will be added to total of the order.
- Rows / columns: set number of rows and columns of images on index print sheet.
- Header: set text to be printed on top of index print
- **Logo:** set an image to be printed as a logo on top right area of the index print. Suitable image is a JPG image with horizontal layout and approximate 300 x 600 pixel size.
- Label on images: it possible to print a sequential number or the file name on top of each thumbnail image. No label printing is also available.
- Min number of photos: orders with less images than what set into this parameter will <u>not</u> trigger index printing.
- Max size (in mm) of the channels to include: print format with at least one side bigger than set value will <u>not</u> trigger index printing.

Receipt

With this setting it is possible to setup an optional receipt printer to release a printed receipt after submitting an order.

Before configuring receipt printer settings, the receipt printer driver must be installed into kiosk Windows operating system.

Receipt	Receipt
f Receipt printer	
Printing mode G Auto	Printer Quantity 9 No Setup 1
Prints the receipt for the customer Prints the receipt for the shop No No) Save a receipt file for each order in this directory
Language used for the receipt Italian / Italiano	/ Save xml order file in this directory
™e DiLand Studio	FAN code template F
d Line1	^d Print the tidet on this channel
Line 2	Print order envelope Print envelope for home orders #4 No No Yes 🕑
OK Cancel	e OK Cancel

- **Receipt printer**: select printer from list of installed printers.
- **Printing mode**: It is possible to select one out of: Auto, XAML, RTF, GDI+. The selection is based on the connected ticket printer capability. If not sure, select the default AUTO. RTF mode is the most compatible mode so it will work with most printers but ticket layout will be simplest. RTF mode doesn't support barcode printing.
- Print the receipt for the customer: if set to "yes" a receipt will be printed at the end of each order.
- Print the receipt for the shop: if set to "yes" a second receipt will be printed for the shop assistant.
- Language: select language to be used for the receipt from a list of available languages.
- Title: Enter title for the receipt to be printed at top of receipt.
- Line 1 and 2: enter text to be printed below title line.
- **Footer**: enter text to be printed at the bottom of the receipt.
- Logo: import a graphic to be used at the top of the receipt.
- Save a receipt file: choose a directory where to save a text file with a copy of order receipt.

Receipt printer connected to another terminal with DiLand Software

- 1) Go to settings menu and go to receipt options.
- 2) From the 'Receipt Printer', select 'Server'.
- 3) Enter computer name or IP address of the terminal with connected ticket printer. Note: DiLand Kiosk or DiLand Studio software must be in execution also on the terminal with connected printer.



4) Click on 'Ok' button to finish.




Frames

Frames (for "Frames" product) allows user to enhance pictures with graphic elements like borders, logos, etc. The file with a frame must be:

- .png with transparent area where the photo will be printed.
- Same size ratio as print format
- Minimum resolution of 10x15cm frame: 1200x1800 pixels.
- Transparent area may have shade.

Example of importing a frame for 6x8 size print.

- 1) Click on frames.
- 2) Click on import files



- 3) It will open system file browser to select the file(s) to be used as graphics for prints with frames.
- 4) Click "open" to import the file(s), click on "close" to close frames import window, close the program and <u>restart</u> the software.
- 5) New Frames are now available if you select "Frames" Product.

ID photo to USB

ID photo to USB is an additional service which can be added to passport print service.

At the end of passport print workflow, customer will be promted to insert his/her USB memory and then images of the order, full and cropped, will be copied to the USB memory.

	anda	-0
	ID photo to USB	
	Enable "ID Photo to USB"	
i(No	
-	Price "ID Photo to USB"	
	€ 0,00	
	OK Cancel	

To enable ID photo to USB set "yes" and, if needed, insert a price for this additional service.

Update local kiosks

DiLand Studio 2.4.43.46				1000 C	o x
Orders History G	onfiguration				
	photo sources	categories	update license		
	photos visualization	index print	export logs		
	steps of each correction command	receipt	check for updates		
	operators	frames	teamviewer		
	import data	id photo to usb	about		
	export data	update local kiosks			
	imports from diland 1				
	hot folders				
	centralized configurations				
	passwords				
	orders to the lab				
	orders				

When products settings are made on DiLand Studio software they need to be transferred to local kiosks. By selecting "update local kiosks" DiLand Studio software will publish the settings and they will be loaded by the kiosks as they will be idle on digital signage screen.

Import of settings by the kiosk could take few seconds to some minutes, depending on number of products and graphics.

Diagnostics

DiLand Studio 2.4.43.46		- 0 X
Orders History Configuration		
System	Products Diagnostics	
initial parameters	output profiles printer status	
privacy	products update firmware	
digital signage	prices orders in process	
photo sources	categories update license	
photos visualization	index print export logs	
steps of each correction command	receipt check for updates	
operators	frames teamviewer	
import data	id photo to usb about	
export data	update local kiosks	
imports from diland 1		
hot folders		(\mathbf{V})

Orders in process

To list the orders which are in process and therefore are not yet printable. All orders with any error condition are listed here.

- 1) Choose "Orders in process".
- 2) Following options are available:
 - <u>Show error</u>: display details about error condition of selected order.
 - <u>Delete all orders in error</u>: all orders with error condition will be definitely deleted.

Printer status

It lists the connected printer(s), media loaded, remaining prints, printer status.

Update firmware

DiLand Studio software will download and install firmware updates for connected DNP printers.

- During firmware update the green light of printer panel will be blinking
- At end of firmware update printer will restart
- Make sure there are no power supply interruptions during firmware update

Export logs

To create a compressed folder containing log files, useful to report eventual problems with the system.

Teamviewer

It will open Teamviewer software to allow remote support. When instructed, please communicate the Teamviewer ID visible on the screen to the service engineer to get the remote support. (*Note: This service requires internet connection*)

Check for updates

By clicking on the button 'Check for updates' the system will search for an update. If there is an update, the software will prompt a message to quit and launch the software.

Update license

In case of installation of new options it may be necessary to update software license. For more information, please contact your retailer.

About...

It will show currently installed software version, options installed and date of expiration of updates



Troubleshooting

Local immediate print product is no longer available

If you are using DNP printers, the software automatically hides the products which can not be processed. Make sure the printer is powered on, with available media, connected to the terminal and ready to print.

